

---

GemStone®

# *GemStone/S 64 Bit Installation Guide*

for HP-UX  
on HP 9000 or HP Integrity Systems

Version 2.3

October 2008

GEMSTONE<sup>™</sup>  
.....S<sup>™</sup>64

---

## INTELLECTUAL PROPERTY OWNERSHIP

This documentation is furnished for informational use only and is subject to change without notice. GemStone Systems, Inc. assumes no responsibility or liability for any errors or inaccuracies that may appear in this documentation.

This documentation, or any part of it, may not be reproduced, displayed, photocopied, transmitted, or otherwise copied in any form or by any means now known or later developed, such as electronic, optical, or mechanical means, without express written authorization from GemStone Systems, Inc.

Warning: This computer program and its documentation are protected by copyright law and international treaties. Any unauthorized copying or distribution of this program, its documentation, or any portion of it, may result in severe civil and criminal penalties, and will be prosecuted under the maximum extent possible under the law.

The software installed in accordance with this documentation is copyrighted and licensed by GemStone Systems, Inc. under separate license agreement. This software may only be used pursuant to the terms and conditions of such license agreement. Any other use may be a violation of law.

Use, duplication, or disclosure by the Government is subject to restrictions set forth in the Commercial Software - Restricted Rights clause at 52.227-19 of the Federal Acquisitions Regulations (48 CFR 52.227-19) except that the government agency shall not have the right to disclose this software to support service contractors or their subcontractors without the prior written consent of GemStone Systems, Inc.

This software is provided by GemStone Systems, Inc. and contributors "as is" and any expressed or implied warranties, including, but not limited to, the implied warranties of merchantability and fitness for a particular purpose are disclaimed. In no event shall GemStone Systems, Inc. or any contributors be liable for any direct, indirect, incidental, special, exemplary, or consequential damages (including, but not limited to, procurement of substitute goods or services; loss of use, data, or profits; or business interruption) however caused and on any theory of liability, whether in contract, strict liability, or tort (including negligence or otherwise) arising in any way out of the use of this software, even if advised of the possibility of such damage.

## COPYRIGHTS

This software product, its documentation, and its user interface © 1986-2008 GemStone Systems, Inc. All rights reserved by GemStone Systems, Inc.

## PATENTS

GemStone is covered by U.S. Patent Number 6,256,637 "Transactional virtual machine architecture", Patent Number 6,360,219 "Object queues with concurrent updating", and Patent Number 6,567,905 "Generational Garbage Collector". GemStone may also be covered by one or more pending United States patent applications.

## TRADEMARKS

**GemStone**, **GemBuilder**, **GemConnect**, and the GemStone logos are trademarks or registered trademarks of GemStone Systems, Inc. in the United States and other countries.

**UNIX** is a registered trademark of The Open Group in the United States and other countries.

**Sun**, **Sun Microsystems**, **Solaris**, and **SunOS** are trademarks or registered trademarks of Sun Microsystems, Inc. All **SPARC** trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. **SPARCstation** is licensed exclusively to Sun Microsystems, Inc. Products bearing SPARC trademarks are based upon an architecture developed by Sun Microsystems, Inc.

**HP** and **HP-UX** are registered trademarks of Hewlett Packard Company.

**Intel** and **Pentium** are registered trademarks of Intel Corporation in the United States and other countries.

**Microsoft**, **MS**, **Windows**, **Windows 2000** and **Windows XP** are registered trademarks of Microsoft Corporation in the United States and other countries.

**Linux** is a registered trademark of Linus Torvalds and others.

**Red Hat** and all Red Hat-based trademarks and logos are trademarks or registered trademarks of Red Hat, Inc. in the United States and other countries.

**AIX** and **POWER5** are trademarks or registered trademarks of International Business Machines Corporation.

Other company or product names mentioned herein may be trademarks or registered trademarks of their respective owners. Trademark specifications are subject to change without notice. All terms mentioned in this documentation that are known to be trademarks or service marks have been appropriately capitalized to the best of our knowledge; however, GemStone cannot attest to the accuracy of all trademark information. Use of a term in this documentation should not be regarded as affecting the validity of any trademark or service mark.

### **GemStone Systems, Inc.**

1260 NW Waterhouse Avenue, Suite 200  
Beaverton, OR 97006

---

## Preface

### About This Documentation

This document explains how to install GemStone/S 64 Bit version 2.3, and how to convert from previous GemStone/S 64 Bit versions or from earlier GemStone/S server products.

For information regarding new and modified features, please refer to the *GemStone/S 64 Bit Release Notes*.

### Terminology Conventions

This document uses the following terminology:

- ▶ The term “GemStone” is used to refer both to the product, GemStone/S 64 Bit, or previous GemStone/S server products; and to the company, GemStone Systems, Inc.

### Typographical Conventions

This document uses the following typographical conventions:

- ▶ Operating system and Topaz commands are shown in **bold** typeface. For example:

**copydbf**

- ▶ Smalltalk methods, GemStone environment variables, operating system file names and paths, listings, and prompts are shown in `monospace` typeface. For example:

`markForCollection`

- ▶ Place holders that are meant to be replaced with real values are shown in *italic* typeface. For example:

*StoneName.conf*

In formal syntax listings, these additional conventions are used:

- ▶ Literals are shown in **bold** typeface. For example:

**tcp**

- ▶ Optional arguments and terms are enclosed in square brackets. For example:

[ *dbName* ]

- ▶ Braces { } mean 0 or more modifiers. For example:

{ *modifier* }

In this example you may list as many modifiers as you wish, but they are not required.

- ▶ Alternative arguments and terms are separated by a vertical bar (pipe). For example:

*gemStoneName* | *netLdiName*

In this example you must specify one name, but not both.

## Technical Support

GemStone provides several sources for product information and support. The product-specific manuals and online help provide extensive documentation, and should always be your first source of information. GemStone Technical Support engineers will refer you to these documents when applicable.

**GemStone Web Site:** <http://support.gemstone.com>

GemStone's Technical Support website provides a variety of resources to help you use GemStone products. Use of this site requires an account, but registration is free of charge. To get an account, just complete the Registration Form, found in the same location. You'll be able to access the site as soon as you submit the web form.

The following types of information are provided at this web site:

**Help Request** allows designated support contacts to submit new requests for technical assistance and to review or update previous requests.

**Documentation** for GemStone/S 64 Bit is provided in PDF format. This is the same documentation that is included with your GemStone/S 64 Bit product.

**Release Notes** and **Install Guides** for your product software are provided in PDF format in the Documentation section.

**Downloads** and **Patches** provide code fixes and enhancements that have been developed after product release. Most code fixes and enhancements listed on the GemStone Web site are available for direct downloading.

**Bugnotes**, in the Learning Center section, identify performance issues or error conditions that you may encounter when using a GemStone product. A bugnote describes the cause of the condition, and, when possible, provides an alternative means of accomplishing the task. In addition, bugnotes identify whether or not a fix is available, either by upgrading to another version of the product, or by applying a patch. Bugnotes are updated regularly.

**TechTips**, also in the Learning Center section, provide information and instructions for topics that usually relate to more effective or efficient use of GemStone products. Some Tips may contain code that can be downloaded for use at your site.

**Community** provides customer forums for discussion of GemStone product issues.

Technical information on the GemStone Web site is reviewed and updated regularly. We recommend that you check this site on a regular basis to obtain the latest technical information for GemStone products. We also welcome suggestions and ideas for improving and expanding our site to better serve you.

You may need to contact Technical Support directly for the following reasons:

- ▶ Your technical question is not answered in the documentation.
- ▶ You receive an error message that directs you to contact GemStone Technical Support.
- ▶ You want to report a bug.
- ▶ You want to submit a feature request.

Questions concerning product availability, pricing, keyfiles, or future features should be directed to your GemStone account manager.

When contacting GemStone Technical Support, please be prepared to provide the following information:

- ▶ Your name, company name, and GemStone/S license number
- ▶ The GemStone product and version you are using
- ▶ The hardware platform and operating system you are using
- ▶ A description of the problem or request
- ▶ Exact error message(s) received, if any

Your GemStone support agreement may identify specific individuals who are responsible for submitting all support requests to GemStone. If so, please submit your information through those individuals. All responses will be sent to authorized contacts only.

For non-emergency requests, the support website is the preferred way to contact Technical Support. Only designated support contacts may submit help requests via the support website. If you are a designated support contact for your company, or the designated contacts have changed, please contact us to update the appropriate user accounts.

**Email: [support@gemstone.com](mailto:support@gemstone.com)**

**Telephone: (800) 243-4772 or (503) 533-3503**

Requests for technical assistance may also be submitted by email or by telephone. We recommend you use telephone contact only for more serious requests that require immediate evaluation, such as a production system that is non-operational. In these cases, please also submit your request via the web or email, including pertinent details such error messages and relevant log files.

If you are reporting an emergency by telephone, select the option to transfer your call to the technical support administrator, who will take down your customer information and immediately contact an engineer.

Non-emergency requests received by telephone will be placed in the normal support queue for evaluation and response.

## 24x7 Emergency Technical Support

GemStone offers, at an additional charge, 24x7 emergency technical support. This support entitles customers to contact us 24 hours a day, 7 days a week, 365 days a year, if they encounter problems that cause their production application to go down, or that have the potential to bring their production application down. For more details, contact your GemStone account manager.

## Training and Consulting

Consulting and training for all GemStone products are available through GemStone's Professional Services organization.

- ▶ GemStone/S training courses are offered periodically at GemStone's offices in Beaverton, Oregon, or you can arrange for onsite training at your desired location.
- ▶ Customized consulting services can help you make the best use of GemStone products in your business environment.

Contact your GemStone account representative for more details or to obtain consulting services.

***Chapter 1. Installing GemStone/S 64 Bit Version 2.3***

Review the Installation Procedure . . . . . 1-1  
Check the System Requirements . . . . . 1-2  
Prepare for Installation . . . . . 1-6  
Set the Environment . . . . . 1-7  
Create the GemStone Key File . . . . . 1-8  
Verify TCP/IP . . . . . 1-9  
Define the NetLDI Service . . . . . 1-9  
Check the /etc/nsswitch.conf system file . . . . . 1-10  
Run the Installation Script. . . . . 1-10  
    Decisions to Make During Installation. . . . . 1-10  
Change System Passwords and Add Users . . . . . 1-13  
Have Users Execute gemsetup . . . . . 1-14  
Install the default TimeZone . . . . . 1-15  
What Next? . . . . . 1-15

***Chapter 2. Upgrading from previous GemStone/S 64 Bit 2.x versions***

Upgrade Strategy. . . . . 2-1  
Upgrade Procedure . . . . . 2-2  
    Prepare for Upgrade . . . . . 2-2  
    Perform the Upgrade. . . . . 2-4  
    Restore Your Site-Specific Settings and Back Up the Repository . . . . . 2-5

### ***Chapter 3. Converting from GemStone/S 64 Bit 1.x***

Conversion Strategy . . . . .	3-2
Conversion Procedure . . . . .	3-2
Preprocessing in Old Environment . . . . .	3-3
Prepare for Conversion . . . . .	3-5
Perform the Conversion and Upgrade . . . . .	3-6
Restore Your Site-Specific Settings and Back Up the Repository . . . . .	3-9

### ***Chapter 4. Converting from GemStone/S 6.x***

Conversion Strategy . . . . .	4-2
Conversion Procedure . . . . .	4-2
Preprocessing in Old Environment . . . . .	4-3
Prepare for Conversion . . . . .	4-5
Perform the Conversion and Upgrade . . . . .	4-6
Restore Your Site-Specific Settings and Back Up the Repository . . . . .	4-9
Detecting Oversize Methods. . . . .	4-10

### ***Chapter 5. Configuring GBS for GemStone/S 64 Bit***

Supported platforms . . . . .	5-2
GemStone/S 64 Bit 2.3 Windows Client Installation . . . . .	5-3
Installing the GemStone/S 64 Bit 2.3 Libraries onto Windows Clients . . . . .	5-3
Installing the GemStone/S 64 Bit 2.3 Libraries onto Unix Clients. . . . .	5-4

# Installing GemStone/S 64 Bit Version 2.3

This chapter describes the procedure for installing GemStone/S 64 Bit version 2.3 on a single machine. If you have enough disk space on a single machine, we recommend that you set up GemStone this way initially to ensure that all the pieces work together. At the end of this chapter, we suggest refinements you might want to make, such as running GemStone in a network configuration.

*NOTE*

*If you are upgrading to this release from a previous version of GemStone/S 64 Bit, or converting from a previous GemStone/S product, follow the instructions in the appropriate chapter of this Installation Guide.*

Adjust the installation to meet your specific needs. The topic “What Next?” on page 1-15 provides references to procedures and related information in the *System Administration Guide for GemStone/S 64 Bit*.

## Review the Installation Procedure

The following list summarizes the steps to install GemStone/S 64 Bit.

- ▶ Check the System Requirements ..... 1-2
- ▶ Prepare for Installation ..... 1-6
- ▶ Set the Environment ..... 1-7
- ▶ Create the GemStone Key File ..... 1-8
- ▶ Verify TCP/IP ..... 1-9
- ▶ Define the NetLDI Service..... 1-9
- ▶ Check the /etc/nsswitch.conf system file..... 1-10
- ▶ Run the Installation Script ..... 1-10
- ▶ Change System Passwords and Add Users ..... 1-13

- ▶ Have Users Execute gemsetup.....1-14

## Check the System Requirements

Before you install GemStone/S 64 Bit, ensure that the following system requirements are satisfied. Systems meeting these requirements are suitable for installing GemStone/S 64 Bit and beginning development, but additional system resources may be necessary to support large applications.

### Platforms

- ▶ HP 9000 workstation, series 800 or higher, with PA RISC 2.0.
- ▶ HP Integrity server, 9000 Rx series or higher, with Itanium 2 9000 series processor.

### RAM

- ▶ At least 1 GB (2 GB recommended)
- ▶ 10 MB for each Gem session process beyond the first two, depending on how the Gem processes are configured

### Swap space

- ▶ At least 1 GB of swap space beyond other system needs (2 GB recommended). In general, your total swap space should be at least twice the RAM installed.

### Disk space

- ▶ Space for the installed distribution files—you need approximately 450 MB for GemStone/S 64 Bit, and additional space for other products.
- ▶ Additional disk space as required for your repository.
- ▶ The repository files should be located on a disk drive that does not contain swap space. Use of multiple disk drives is advisable for servers.

### Operating system

- ▶ HP-UX version 11.11 on PA-RISC, or HP-UX version 11.23 or 11.31 on Itanium.
- ▶ For this release of GemStone/S 64 Bit, the following HP patches were installed for the specified Operating System and Platform:

HP-UX 11.11 on PA-RISC:

BUNDLE11i - B.11.11.0306.1  
FEATURE11-11 - B.11.11.0209.5  
GOLDAPPS11i - B.11.11.0606.446  
GOLDBASE11i - B.11.11.0606.446  
HWEnable11i - B.11.11.0509.430  
PHCO\_30544 - 1.0  
PHCO\_33142 - 1.0  
PHCO\_33711 - 1.0  
PHCO\_34196 - 1.0  
PHCO\_34207 - 1.0  
PHCO\_34240 - 1.0

PHCO\_34255 - 1.0  
PHCO\_34348 - 1.0  
PHCO\_36097 - 1.0  
PHKL\_34161 - 1.0  
PHKL\_34254 - 1.0  
PHKL\_34518 - 1.0  
PHKL\_34665 - 1.0  
PHSS\_32971 - B.11.11.34  
PHSS\_33892 - 1.0

HP-UX 11.23 on Itanium:

BUNDLE11i - B.11.23.0409.3  
FEATURE11-11 - B.11.23.0712.070  
QPKAPPS- 11.23.0712.070a  
QPKBASE - B.11.23.0712.070a4  
HWEnable11i - B.11.23.0712.070  
PHKL\_37755 - 1.0

HP-UX 11.31 on Itanium:

FEATURE11-11 - B.11.31.0803.318b  
QPKBASE - B.11.31.0803.318a  
HWEnable11i - B.11.31.0803.318a

► Configure the operating system kernel:

- a. Invoke SAM on HP-UX 11.11 or 11.23, or SMH on HP-UX 11.31.
- b. Ensure that asynchronous I/O is enabled.

On HP-UX 11.11 and 11.23:

From the Drivers menu of Kernel Configuration, select `asyncdsk`, then press Return.

If the returned status is “out,” go to the Actions menu and choose Add to Kernel. Have SAM rebuild the kernel and reboot.

on HP-UX 11.31:

If asynchronous I/O is listed as “no”, select the modules menu of Kernel Configuration, select `asyncdsk`, press “m” to modify, then press Return.

Change the state of the module to “static” and answer the questions. Go to the Actions menu and choose Add to Kernel. Have SMH rebuild the kernel and reboot

- c. Set the following kernel parameters from the Configurable Parameters menu:
  - Set the parameter `fs_async` to 1.
  - Set the parameter `max_mem_window` to 256.
  - A file descriptor limit of 1024 is adequate for up to about 500 GemStone users. Each user session requires two file descriptors, and others are needed for extents, transaction logs, and overhead. Consequently, you may need to set the `nfile` parameter to a larger value, such as 2048. *Use caution and increase the default setting only when necessary because doing so can have system side effects.*
  - The parameter `nflocks` sets the possible number of file/record locks in the system. Like `nfiles` (above), this parameter limits the number of extents and user

sessions that GemStone can support at one time. We recommend the same setting for `nlocks` as for `nfiles`.

- ▶ HP-UX 11.11 only: Set the `maxusers` parameter to 512. Several other parameters are automatically scaled from this one.
- ▶ The parameter `semmni` sets the number of semaphore identifiers in the system. This parameter limits the number of GemStone shared page caches on the node because each shared page cache uses one identifier. There will be one shared page cache on the node for each local Stone repository monitor. There will also be one for each remote Stone (that is, each Stone on another node) if users log in to that Stone through a Gem session process on the local node. A setting of 2048 should be adequate for most installations.
- ▶ The parameter `semmns` sets the total number of semaphores in the system. This parameter limits the total number of GemStone sessions on a node. The default may not be adequate for some GemStone installations, especially if other software uses semaphores or if more than one shared page cache will be present. A suggested value is 4096.

The parameter `shmmax` sets the maximum shared memory segment size. This will limit the maximum size of Shared Page Cache you will be able to use. We recommend that the maximum shared memory segment be set to a value larger than your desired Shared Page Cache size, and not more than 75% of your real memory size. For example, if you have 8192 MB of real memory:

```
8192 MB * .75 = 6144 MB
6144 MB * 2**20 = 6442450944 bytes
```

- ▶ The parameter `shmmni` sets the number of shared memory identifiers in the system. We suggest that you set `shmmni` the same as `semmni`, above.
- ▶ We recommend the following additional settings, to avoid the risk of running out of system resources:
 

```
maxdsiz 4294963200
maxdsiz_64bit 4396972765184
maxrsessiz 401604608
maxrsessiz_64bit 1073741824
maxssiz 401604608
maxssiz_64bit 2147483648
maxtsiz 1073741824
maxtsiz_64bit 4398046511103
maxuprc 10000
```
- ▶ On HP-UX 11.23 and 11.31, no modifications are recommended for the tunable kernel AIO settings.
  - d. Exit SAM.
  - e. Find the character device major number for `asyncdsk`:
 

```
# lsdev
```
  - f. Create a device special file:
 

```
# mknod async c majorNumber 0x000000
```

 where *majorNumber* is the number returned by `lsdev`.

*NOTE*

*During installation, if you see a message similar to `HostAioInit failure: cannot open /dev/async`, asynchronous I/O is not enabled.*

- g. Give the user running GemStone (or all users) the MLOCK privilege by running one of the following commands as root:

```
# setprivgrp userId CHOWN MLOCK
or
#setprivgrp -g CHOWN MLOCK
```

To have these privileges assigned to a user group when the system boots, put the following lines in the file `/etc/privgroup`:

```
groupname CHOWN
groupname MLOCK
```

- ▶ To use extents larger than 2 GB in the file system, the file system must be designated as a Large Files file system. When creating a new file system with SAM or SMH, enable the Large File System Allow parameter. To convert an existing HFS file system from a “nolargefiles” file system to a “largefiles” file system, see the documentation for `fsadm`. We recommend that you pregrow such extents to a size greater than 2 GB so that any configuration difficulty is detected when the server is first started.
- ▶ The configuration option `SHR_PAGE_CACHE_SIZE_KB` defines the size (in KBytes) of extent page space in the shared page cache. The maximum acceptable value for this configuration option is limited by system memory, kernel configurations, and cache space allocated by `SHR_PAGE_CACHE_NUM_PROCS`.

For more general information about these and other configuration options, see Appendix A of the *System Administration Guide for GemStone/S 64 Bit*.

## System clock

- ▶ The system clock must be set to the correct time. When GemStone opens the repository at startup, it compares the current system time with the recorded checkpoint times as part of a consistency check. A system time earlier than the time at which the last checkpoint was written may be taken as an indication of corrupted data and prevent GemStone from starting. The time comparisons use GMT.

## TCP keepalive option

- ▶ GemStone processes ordinarily use the TCP `keepalive` option to determine how long they will wait after communications activity ceases unexpectedly. This setting can be useful for reaping stale RPC Gems, but the operating system default may not be appropriate for this purpose. For further information, refer to your operating system documentation.

## C/C++ Compiler

PA-RISC:

- ▶ aCC: HP ANSI C++ B3910B A.03.73

Itanium:

- ▶ HP C/aC++ B3910B A.06.17 [Mar 4 2008]

GemStone requires a C/C++ compiler only if you are developing C or C++ code for user actions or for a C or C++ application. This compiler is required only for development work, not for execution.

## Debugger

PA-RISC:

- ▶ HP gdb 5.9 for PA-RISC 2.0 (wide), HP-UX 11.00

Itanium:

- ▶ HP gdb 5.8 for HP Itanium (32 or 64 bit) and target HP-UX 11.2x

A C debugger can be useful to allow problem analysis by GemStone consulting or Technical Support. It also may allow you to debug your C user actions. It is not required for GemStone execution.

## Prepare for Installation

Perform the following steps to prepare the machine to receive the GemStone/S 64 Bit software. Although most steps require root login, we recommend that you perform the initial step as the GemStone administrator.

These are the portions of the system that are affected by the installation of GemStone:

`/dev/rdsk`

Optional raw partitions for repository extents and transaction logs

`/etc/services`

Internet services database

`/InstallDir/GemStone64Bit2.3.0-hppa.hpux`

`/InstallDir/GemStone64Bit2.3.0-ia64.hpux`

Location of the object server software

`/opt/gemstone`

Default location for server lock files, and log files for GemStone network servers (NetLDIs)

`/usr/gemstone`

Alternative location for lock and log files, for compatibility with previous products; `/opt/gemstone` is created unless `/usr/gemstone` already exists

1. As the GemStone administrator, log in to a machine that has adequate resources to run GemStone and that owns the disk on which you are going to install the GemStone files.

### NOTE

*Do not copy the files as root. The ownerships that were in effect when the distribution media was created are preserved, and this might result in file permission errors for users at your site.*

2. Determine that adequate swap space is available:

‡ `/etc/swapinfo`

3. Check the free disk space and determine the disk drive and partition on which you will install the GemStone software.

To list all disk partitions, along with the amount of free space in each partition:

```
% bd
```

We recommend that you avoid choosing either an NFS-mounted partition or one containing UNIX swap space for the initial installation. Mounted partitions can result in executables running on the wrong machine and in file permission problems. Existence of swap space on the same drive can dramatically slow GemStone disk accesses.

4. Select an installation directory, *InstallDir*, and make this directory the current working directory.
5. GemStone/S 64 Bit is provided as a zipped archive file with a name similar to `GemStone64Bit2.3.0-hppa.hpux.zip` or `GemStone64Bit2.3.0-ia64.hpux.zip`. Move this distribution file to the directory location in which GemStone will be installed, *InstallDir*.
6. Unzip the distribution file using `unzip`. For example:

```
% unzip GemStone64Bit2.3.0-hppa.hpux.zip
```

The *InstallDir* now contains a GemStone directory with a name similar to `GemStone64Bit2.3.0-hppa.hpux` or `GemStone64Bit2.3.0-ia64.hpux`.

In addition to several subdirectories, this directory also contains two text files: `PACK-ING`, which lists all of the GemStone files, and `version.txt`, which identifies this particular product and release of GemStone.

*NOTE*

*The GemStone man pages in the `doc` directory cannot be accessed by using `man -f` or `man -k` unless `/usr/share/lib/what` is re-created to include them. The installation script does not perform this action.*

7. Log in as root.

*NOTE*

*Although you can complete the installation as a non-root user, we do not recommend this. During installation, GemStone system security is established through file permissions and process attributes. To ensure that the installation is successful, **you must install as root**. If you later decide to change the security of your GemStone system, see Chapter 1 of the System Administration Guide for GemStone/S 64 Bit, which explains the concept of GemStone server file permissions and how to change them.*

## Set the Environment

Perform the following steps to properly configure the operating environment.

1. Set the environment variable `GEMSTONE`.
  - a. If more than one installation of any GemStone/S product resides on this machine, check for existing GemStone environment variables:

```
% env | grep GEM
```

All GemStone environment variables are displayed.

- b. If any environment variables exist, you must specifically unset each one.

C shell:

```
% unsetenv GEMSTONE GEMSTONE_SYS_CONF \  
GEMSTONE_EXE_CONF GEMSTONE_LOG GEMSTONE_LANG
```

Bourne or Korn shell:

```
$ unset GEMSTONE GEMSTONE_SYS_CONF GEMSTONE_EXE_CONF \  
GEMSTONE_LOG GEMSTONE_LANG
```

- c. Set the environment variable GEMSTONE to the *full pathname* (starting with a slash) of your new GemStone installation directory.

C shell:

```
% setenv GEMSTONE InstallDir/GemStone64Bit2.3.0-hppa.hpux
```

or

```
% setenv GEMSTONE InstallDir/GemStone64Bit2.3.0-ia64.hpux
```

Bourne or Korn shell:

```
$ GEMSTONE=InstallDir/GemStone64Bit2.3.0-hppa.hpux  
$ export GEMSTONE
```

or

```
$ GEMSTONE=InstallDir/GemStone64Bit2.3.0-ia64.hpux  
$ export GEMSTONE
```

## Create the GemStone Key File

To run GemStone, you must create a key file. Instructions and information to create this file were shipped with the distribution media. If either of these materials is missing, call GemStone Contract Administration.

1. Change the permissions on the directory `$GEMSTONE/sys` so that you can create the file:

```
% cd $GEMSTONE/sys  
% chmod 755 .
```

2. Using a text editor and the information provided, create the key file `$GEMSTONE/sys/gemstone.key`.

3. Change the file and directory permissions so that they are no longer writable:

```
% chmod 555 gemstone.key  
% chmod 555 .
```

## Verify TCP/IP

To run GemStone, TCP/IP must be functioning, even if your machine is not connected to a network.

1. Verify that TCP/IP networking software is functioning (1 is the number 1):

```
% /etc/ping hostname 8 1
```

where *hostname* is the name of your machine. If **ping** responds with statistics, TCP/IP is functioning.

## Define the NetLDI Service

The NetLDI service, by default `gs64ldi`, should be defined in your TCP/IP network database. This is required for certain kinds of local sessions, or any client on a remote machine, to log into GemStone. For clients on remote machines, the same NetLDI service name and port number must be defined on the remote machine.

### NOTE

*If you are upgrading from a previous version, you might need to keep the NetLDI for that version running. You may need to select a distinct name and port for the NetLDI for GemStone/S 64 Bit 2.3, rather than using the default `gs64ldi`.*

1. Determine whether the `gs64ldi` service is already defined:

```
% ypcat services | grep gs64ldi
```

If it is defined, skip the rest of this procedure and continue with the installation at “Run the Installation Script” on page 1-10.

If it is not defined, continue performing this procedure.

2. Determine which TCP/IP network database (local or NIS) is in use:

```
% ypwhich
```

If the program is missing or you see an error message when you run it, you can assume that your machine is using a local copy of the TCP/IP network database instead of a copy provided by NIS. Perform the following step on your local copy of the network database (the file `/etc/services`).

If NIS is running, have your UNIX system administrator perform the following steps.

3. Add an entry similar to the following to the network database:

```
gs64ldi 50377/tcp #GemStone/S 64 Bit 2.3
```

Choose a port number that is not being used by another service. The port number should be in the range `49152 <= port <= 65535`, to conform to IANA standards (<http://www.iana.org/assignments/port-numbers>).

4. If NIS is running, propagate the change to the network database to the rest of the network.
5. If NIS is not running, but several machines will be running GemStone, have the UNIX system administrator update the network database for each machine. Note that the port number must be the same for every machine.

## Check the /etc/nsswitch.conf system file

Make sure there is a services entry in the /etc/nsswitch.conf system file. This addition allows the netldi service name to resolve to the appropriate port number.

The following line in /etc/nsswitch.conf is for use when services can be resolved via a local /etc/service file:

```
services: files
```

The next example in /etc/nsswitch.conf is for use when services can be resolved via the local /etc/services file and then via the NIS server:

```
services: files [NOTFOUND=continue UNAVAIL=continue] nis
```

## Run the Installation Script

Invoke the installation script from the install subdirectory:

```
% cd $GEMSTONE/install
% ./installgs
```

installgs is an interactive script that analyzes your system configuration and makes suggestions to guide you through installing GemStone on your machine.

### NOTE

*You can usually terminate execution of the installation script with Ctrl-C without risk to your files. When it is not safe to do so, the message Please do not interrupt appears on the screen. If this happens, wait for the message now it is OK to interrupt before you interrupt the script. You can run the script again from the beginning as many times as necessary.*

## Decisions to Make During Installation

During installation, you are asked several questions. The entire installation dialog is not reproduced here, but the main points are addressed. Some questions may not be asked, depending on answers to previous questions.

Whenever you are asked to answer “yes” or “no,” answer with **y** or **n**. When the script offers a default answer in square brackets (such as “[y]”), press Enter to accept the default.

## Verify the Release Tree?

Do you want the installation script to verify your GemStone release tree?

This process takes a few minutes, but it’s a good idea to ensure that the files were transferred from your distribution media without error.

Default: Verify the installation tree.

The GemStone installer will attempt to verify some system requirements on your system. Some of the verifications may issue warnings of the form:

```
./installgs[52]: test: Specify a parameter with this command.  
./installgs[52]: -q: not found.  
./installgs[260]: test: Specify a parameter with this command.
```

Unless an explicit installation failure is returned, the installation will complete successfully, and the above warnings may be ignored.

## Do you want the installation script to set up directories for server lock files and NetLDI logs?

The default location for server lock files and NetLDI log files is `/opt/gemstone`, although for compatibility with earlier products `/usr/gemstone` is used only if it exists. If the environment variable `GEMSTONE_GLOBAL_DIR` is defined to point to a valid directory, this overrides the default server lock files and log file location; however, all Gemstone processes that will interact on this machine must have this environment variable set to the same directory.

If these directories do not exist, the installation script offers to create `/opt/gemstone` and the subdirectories `locks` and `log`. Then, the script offers to set access (770) to these directories.

If you answer **no** to creating the directories, you must create them (or provide a symbolic link) before starting the server.

## Do you want the installation script to set the owner and group for all the files in the GemStone distribution?

If you answer **yes**, the script will prompt you for the owner and group you want to use. Refer to Chapter 1 of the *System Administration Guide for GemStone/S 64 Bit* for more information about setting owner and group permissions.

If you answer **no**, the permissions will remain the same as when the files were extracted from the distribution media.

## Do you want the installation script to protect the repository file?

The default, which we recommend, gives only the owner read and write access (600) through ordinary UNIX commands. Other users can read and write the repository through a GemStone session. If you choose not to protect the repository, the `setuid` bit is cleared from all executables, which causes them to run under ownership of the user who invokes them.

Default: Set the repository permission to 600, and leave the `setuid` bit applied.

## Allow NetLDI to Run as Root?

Do you want the installation script to allow non-root users to start a NetLDI that runs as root?

The NetLDI is a network server that permits remote processes to interact with the repository. There are two ways to set up a NetLDI so that it can provide services to all GemStone users: it can run as root, or it can run in guest mode with a captive account.

- ▶ To run NetLDIs as root, accept the default “yes” response. Ownership of the NetLDI executable is changed to root, and the setuid bit is set. Any GemStone user will be able to start a NetLDI process that is accessible to all GemStone users because it will always run as root. For certain services, users will need to authenticate themselves by supplying a password. Alternatively, answer “no” but log in as root before starting the NetLDI.

If the NetLDI uses a port number less than 1024, it must run as root.

- ▶ To run NetLDIs in guest mode with a captive account, answer “no” to the prompt, because those modes are not permitted if the NetLDI runs as root. “Guest mode” means that GemStone users do not have to supply a UNIX password to use NetLDI services. The “captive account” is an account that owns all processes the NetLDI starts; typically, it is the GemStone administrative account that owns the files. You must start the NetLDI while logged in as that account.

Default: Change ownership of the `netldi` executable to root, and set its setuid bit.

## Set up an Extent?

Do you want the installation script to set up an extent now?

GemStone is distributed with a read-only copy of the initial repository in `$GEMSTONE/bin/extent0.dbf`. Before you can start GemStone, this file must be copied to a suitable location and made writable. The script offers to copy the file to its default location of `$GEMSTONE/data`.

If you are a new GemStone user, we recommend that you answer **y**. If you are an existing GemStone user, you might prefer to answer **n**, then copy the extent to a different location yourself. (If you choose a location other than the default, you must edit your configuration file before starting GemStone. For information, see the *System Administration Guide for GemStone/S 64 Bit*.)

Default: Place a writable copy of `extent0.dbf` in `$GEMSTONE/data`.

## Start a NetLDI?

Do you want the installation script to start a NetLDI?

If you prefer, you can start these processes manually at any time.

Almost every host needs a NetLDI. You must start a NetLDI when the Stone repository monitor or Gem session processes will run on this machine.

You can start a NetLDI that runs as root by answering **yes** to this prompt and the confirmation that follows. However, if you want to start the NetLDI in guest mode with a captive account, you must do that after completing the installation. For more information about guest mode with captive account, see Chapter 3 of the *System Administration Guide for GemStone/S 64 Bit*.

Default: Do not start a NetLDI at this time.

## Start an Object Server?

As root, you cannot start an object server, but the script offers to start one as another user. You will start the server later in the installation, so answer **no**.

Default: Do not start an object server at this time.

Log out as root.

## Change System Passwords and Add Users

After installing GemStone/S 64 Bit, you must change the passwords for the three administrative users: DataCurator, SystemUser, and GcUser. (The initial password for each is `swordfish`.) The DataCurator account is used to perform system administration tasks. The SystemUser account ordinarily is used only for performing GemStone system upgrades. The GcUser account is used by the garbage collection task, which runs automatically as a separate login. Access to each of these accounts should be restricted.

Chapter 6 of the *System Administration Guide for GemStone/S 64 Bit* tells you how to change the passwords and set up accounts for other GemStone users.

You must then establish GemStone accounts for each of your system's users.

The script `makeusers` in the `$GEMSTONE/install` directory helps you change the system passwords and add users. Note that the `makeusers` script assumes that the system passwords are as yet unmodified from their initial values of `swordfish`. Because `makeusers` modifies the system passwords, you can run the script only once on a given repository. To change system passwords or add more users at a later time, refer to the procedures in the *System Administration Guide for GemStone/S 64 Bit*.

### NOTE

*The actions described in this procedure affect only the repository whose name you enter while running the script `makeusers`.*

1. Ensure that the GemStone environment variables are set for version 2.3:

```
% env | grep GEM
```

If necessary, set the environment variables as detailed in "Set the Environment" on page 1-7.

2. Invoke the script `gemsetup`.

C shell:

```
% source $GEMSTONE/bin/gemsetup.csh
```

Bourne or Korn shell:

```
$ . $GEMSTONE/bin/gemsetup.sh
```

The script defines the GemStone environment for users by modifying the `PATH` and `MANPATH` variables to include `$GEMSTONE/bin` and `$GEMSTONE/doc`, respectively.

3. Start the repository monitor (Stone). You must do this from a working directory for which you have write privilege. For instance:

```
% cd $HOME  
% startstone
```

4. Invoke the script `makeusers`:

```
% cd $GEMSTONE/install  
% ./makeusers
```

The script prompts you for the name of your Stone (the default is `gs64stone`), new administrative passwords, and names of the users you want to create. The password for new users will be set to `gemstone`.

The script writes the information you supply to a file that can be read by Topaz, an interactive GemStone interface that you can use for system administration. Topaz deletes the file when it finishes with it. By default, this file is `newusers.topaz`, created in your `$HOME` directory. If you specify another file, be sure to give a full path-name. (You cannot create a file in the `install` directory unless you made the directory writable during installation.)

5. When the script `makeusers` has finished, run the linked version of Topaz and read in the file that the script created.

- a. Invoke linked Topaz:

```
% topaz -l
```

- b. Read in the file containing the new users:

```
topaz> input $HOME/newusers.topaz
```

Topaz reads in the file, displays GemStone's new settings, deletes `$HOME/newusers.topaz`, and logs you out of GemStone.

- c. Exit Topaz:

```
topaz> exit
```

## Have Users Execute gemsetup

The directory `$GEMSTONE/bin` contains two files, `gemsetup.sh` and `gemsetup.csh`, to help set a user's environment. These files define the GemStone environment for users by modifying the `PATH` and `MANPATH` variables to include `$GEMSTONE/bin` and `$GEMSTONE/doc`, respectively.

After GemStone/S 64 Bit 2.3 has been installed, you should notify each GemStone user of the installation and explain how to use the `gemsetup` files.

### NOTE

*This procedure applies to users ONLY. Each user must perform this procedure before running GemStone.*

1. Set the environment variable `GEMSTONE` to the *full pathname* (starting with a slash) of the GemStone/S 64 Bit 2.3 directory.

C shell:

```
% setenv GEMSTONE InstallDir/GemStone64Bit2.3.0-hppa.hpux
```

or:

```
% setenv GEMSTONE InstallDir/GemStone64Bit2.3.0-ia64.hpux
```

Bourne or Korn shell:

```
$ GEMSTONE=InstallDir/GemStone64Bit2.3.0-hppa.hpux
```

```
$ export GEMSTONE
```

or:

```
$ GEMSTONE=InstallDir/GemStone64Bit2.3.0-ia64.hpux
$ export GEMSTONE
```

2. Invoke the script `gemsetup`.

C shell:

```
% source $GEMSTONE/bin/gemsetup.csh
```

Bourne or Korn shell:

```
$ . $GEMSTONE/bin/gemsetup.sh
```

3. If you will use GemStone frequently, consider adding to your login shell's initialization file (`.cshrc` or `.profile`) the environment variable `GEMSTONE` and the command `gemsetup`. This way, the GemStone environment is automatically configured every time you log in or create a login shell. It overrides any other GemStone path settings.

#### NOTE

*If you use the Korn shell and your `.profile` contains commands that are not POSIX-compliant, you might encounter errors when a shell is initialized. To remedy this situation, place the non-compliant commands within a conditional, such as the following:*

```
hash -r 2>/dev/null
status=$?
if [ $status -ne 0 ]; then
    # Place Korn-shell-specific initialization here
fi
```

## Install the default TimeZone

GemStone/S 64 Bit is shipped with a default time zone of US Pacific. If you are in another Time Zone, edit the file `installtimezone.txt` in the GemStone upgrade directory, then file it in as `SystemUser`.

## What Next?

This chapter has guided you through installation of GemStone/S 64 Bit 2.3 in an initial configuration that is sufficient to create a basic repository and begin setting up user accounts. The objective has been to get a simple, default configuration up and running.

You might consider performing the following tasks:

- ▶ To modify the initial object server configuration to one that is more efficient for your particular needs, refer to Chapter 1 of the *System Administration Guide for GemStone/S 64 Bit*. This chapter contains sample configurations, from small to large, and also contains detailed information about how to tailor these configurations to your own system.
- ▶ To modify the configuration of Gem session processes and to ensure that users have the necessary permissions to access the shared page cache and the extents, refer to Chapter 2 of the *System Administration Guide for GemStone/S 64 Bit*.

- ▶ If you are going to operate in a network environment, Chapter 3 of the *System Administration Guide for GemStone/S 64 Bit* has additional information about the GemStone network server (NetLDI), how to handle user authentication, how to share software over the network, and how to set up some common configurations.
- ▶ To start and stop the GemStone object server, refer to instructions in Chapter 4 of the *System Administration Guide for GemStone/S 64 Bit*.

# *Upgrading from previous GemStone/S 64 Bit 2.x versions*

This chapter describes how to upgrade an existing GemStone/S 64 Bit 2.x installation to GemStone/S 64 Bit version 2.3. GemStone/S 64 Bit version 2.3 supports upgrade from GemStone/S 64 Bit versions 2.0.x (2.0.4 or later), 2.1.x (2.1.4 or later), and 2.2.x (2.2.5 or later). If you are upgrading from GemStone/S 64 Bit 1.x, which requires conversion, or from a different GemStone/S server product, see the appropriate chapter for conversion instructions.

As part of the upgrade process, you:

- ▶ Modify application classes and methods that run in GemStone/S 64 Bit so they work properly with the version 2.3 classes and methods.
- ▶ Modify your application's client code as necessary. This code may be in C, C++, or client Smalltalk.
- ▶ If you are upgrading from v2.0.x, ensure that you have the TimeZone2007 patch installed.
- ▶ File out the changes to GemStone kernel classes.
- ▶ Upgrade your repository per the instructions starting on page 2-2.
- ▶ File in your GemStone kernel class changes.
- ▶ Recompile and relink any C or C++ user actions or client applications.
- ▶ Reload client Smalltalk images.

## **Upgrade Strategy**

We recommend that you perform the upgrade twice: first a pilot upgrade and then the production upgrade. With this strategy, you can keep your version 2.x production system running while you familiarize yourself with the upgrade process. The pilot upgrade may be performed on any GemStone/S 64 Bit 2.x test repository.

## Upgrade Procedure

The following list summarizes the steps necessary to perform the upgrade to GemStone/S 64 Bit version 2.3.

- ▶ Prepare for Upgrade.....2-2
- ▶ Perform the Upgrade.....2-4
- ▶ Restore Your Site-Specific Settings and Back Up the Repository .....2-5

### NOTE

*The following instructions use the version number 2.2.5.4 to represent any version from which upgrade is supported. The procedure is the same regardless of which version you have.*

## Prepare for Upgrade

Perform the following steps to prepare for the upgrade.

1. File out any modifications or additions you made to GemStone/S 64 Bit kernel class methods by using the Topaz command **fileout**. For more information about fileout, see the *GemStone Topaz Programming Environment*.

You will need to carefully compare these changes with GemStone/S 64 Bit 2.3 kernel methods to determine whether your changes are still necessary or appropriate.

2. If you are upgrading from version 2.0.x, verify that you have the TimeZone2007 patch installed. This patch provides a new implementation of TimeZone, supporting the 2007 Daylight Savings Time changes in the US. You must install this patch prior to upgrading, even if you do not require the TimeZone changes. The patch is available for download at:

[http://support.gemstone.com/gemstone\\_s/downloads/patches/timezone/index.html](http://support.gemstone.com/gemstone_s/downloads/patches/timezone/index.html)

You do not need to execute the script `timezone.txt`, nor install a new TimeZone instance, in order to perform the conversion.

### NOTE

*Attempts to convert without previously installing the TimeZone2007 patch may coredump.*

3. Install GemStone/S 64 Bit 2.3 to a new installation directory, separate from the installation directory for version 2.2.5.4, as described in Chapter 1 of this Installation Guide.
4. Configure GemStone/S 64 Bit 2.3 the way you expect to use it — that is, with the appropriate extent locations and sizes.
5. Ensure that adequate space is available for extents, transaction logs, and a backup during the upgrade:

⌘ **bdf**

You must provide space for the following:

- ▶ Your version 2.2.5.4 extents and transaction logs.
- ▶ Your version 2.3 extents and transaction logs.

6. Log in to the version 2.2.5.4 system and reset the SystemUser password to 'swordfish':

```
topaz 1> printit
(AllUsers userWithId: #SystemUser) password: 'swordfish' .
System commitTransaction .
%
```

The upgrade script logs in with the SystemUser account and the default password.

7. Halt all user activity on the repository you are going to upgrade:
  - a. Log in to Topaz as DataCurator.
  - b. Force all other users off the system:

```
topaz 1> printit
System stopUserSessions.
%
```

#### CAUTION

*You MUST file out any changes that you have made to the GemStone/S 64 Bit kernel classes in order to preserve these changes in version 2.3. Also, consider saving important modified files, such as configuration files, that will be overwritten during the upgrade.*

8. File out any modifications or additions you made to GemStone/S 64 Bit version 2.2.5.4 kernel class methods by using the Topaz command **fileout**. For more information about fileout, see the *GemStone/S 64 Bit Topaz Programming Environment*.
9. You must now shut down the Stone:

```
% stopstone stone2254
```

where *stone2254* is the name of the version 2.2.5.4 stone on this machine. The repository must be cleanly shut down before it can be restarted under version 2.3

10. Set up the version 2.3 environment.

Set the environment variables required for the upgrade.

C shell:

```
% setenv GEMSTONE InstallDir23
% set path = ($GEMSTONE/bin $path)
% setenv upgradeLogDir tempDir
```

Bourne or Korn shell:

```
$ GEMSTONE=InstallDir23
$ export GEMSTONE
$ export PATH=$GEMSTONE/bin:$PATH
$ upgradeLogDir=tempDir
$ export upgradeLogDir
```

where *InstallDir23* is the GemStone/S 64 Bit version 2.3 installation and *tempDir* is a temporary directory for which you have write permission.

#### NOTE

*Use a separate log directory for each repository you convert. A repository may contain multiple extents.*

11. Copy your version 2.2.5.4 extent files into the location specified by the configuration file option `DBF_EXTENT_NAMES`:
  - a. Using a text editor, open the configuration file that the version 2.2.5.4 repository uses.
  - b. Locate the last occurrence of the option `DBF_EXTENT_NAMES`, and note its value, a list of `.dbf` files.
  - c. Copy each `.dbf` file to the noted location in the version 2.3 installation. For example:
 

```
% cp InstallDir2254/data/extent0.dbf 23location
% cp InstallDir2254/data/extent1.dbf 23location
% cp InstallDir2254/data/extent2.dbf 23location
```

 where *23location* is the location specified by `DBF_EXTENT_NAMES` in the configuration file that will be used in version 2.3.
12. Before upgrading, ensure that there are no transaction logs from a previous version of GemStone/S 64 Bit in any of the transaction log locations specified in the configuration file that will be used by version 2.3. Transaction logs from earlier versions are not compatible with version 2.3. If the transaction log directories will be reused for version 2.3, any transaction logs should be deleted or copied elsewhere.

## Perform the Upgrade

1. Start the 2.3 Stone on the 2.2.5.4 extents you just copied:

```
% startstone stoneName23
```

2. Ensure you are in a directory to which you have write permission, and run the upgrade script.

The upgrade is performed by the script `upgradeImage`. This script has optional switches to specify the stone name and to set to size of the `GEM_TEMPOBJ_CACHE_SIZE` used for the upgrade process.

```
upgradeImage [-h] [-c <cacheSize>] [-s <stoneName>]
```

`-h` prints this usage information.

`-c <cacheSize>` sets the size of the `GEM_TEMPOBJ_CACHE_SIZE`; if this is not used, the script will default to use a value of 100000.

`-s <stoneName>` sets the name of the running stone to upgrade; if this option is not used, the script will default to **gs64stone**.

For example,

```
% upgradeImage -s stoneName23
```

The script will prompt you to press the return key to begin.

3. The script invokes subordinate scripts to complete the upgrade. The upgrade process will take some time. You can examine the progress, if desired, by examining the file `$GEMSTONE/upgradeImage.out`.

The script should complete with the message:

```
Upgrade completed. No errors detected.
```

If not, please preserve the Stone log file and the contents of `$upgradeLogDir`. Contact your internal GemStone support person or GemStone Technical Support.

## Restore Your Site-Specific Settings and Back Up the Repository

1. Reinstall any other GemStone products that modify kernel classes.  
If you use GemConnect, you must install it again at this time. Use the procedure in the installation guide for this product.
2. Log in to GemStone/S 64 Bit version 2.3 as DataCurator.
3. Change the password for SystemUser, which you changed to `swordfish` prior to the conversion, back to its previous value. Also, change the passwords for GcUser and DataCurator, which were reset by the conversion process, back to the version 2.2.5.4 value:

```
topaz 1> printit
(AllUsers userWithId: 'SystemUser') password: '2254Password'.
(AllUsers userWithId: 'GcUser') password: '2254Password'.
(AllUsers userWithId: 'DataCurator') password: '2254Password'.
System commitTransaction
%
```

where `2254Password` is the account password used in GemStone/S 64 Bit version 2.2.5.4.

The upgraded repository is now usable. Other users can log in to assist with the following steps.

4. If you have modified any kernel class methods of the previous version, carefully compare your changes with version 2.3 kernel methods to see whether your changes are still necessary or appropriate. If so, file in the changes and commit.
5. Create a full backup of the upgraded repository. For details, see the *System Administration Guide for GemStone/S 64 Bit*.
6. If you are using GBS clients, configure these to use the version 2.3 client libraries. See Chapter 5, 'Configuring GBS for GemStone/S 64 Bit' for details.



# Converting from GemStone/S 64 Bit 1.x

This chapter describes how to convert an existing GemStone/S 64 Bit 1.x installation to GemStone/S 64 Bit version 2.3. Upgrading from GemStone/S 64 Bit 2.x does not require conversion; if you are upgrading from version 2.x, or converting from another GemStone/S server product, see the appropriate Chapter of this Installation Guide.

GemStone/S 64 Bit version 2.3 supports conversion from GemStone/S 64 Bit versions 1.2 and later.

As part of the conversion process, you:

- ▶ Modify classes and methods that run in GemStone so they work properly with the GemStone/S 64 Bit classes and methods.
- ▶ Modify your application's client code as necessary. This code may be in C, C++, or client Smalltalk.

*NOTE*

*In order to use GemBuilder for Smalltalk (GBS) with the GemStone/S 64 Bit v2.3 server, you may need to upgrade your GBS version, and configure it correctly for use with GemStone/S 64 Bit. See the supported versions and configuration instructions in Chapter 5 of this Installation Guide.*

- ▶ File out the changes to GemStone kernel classes.
- ▶ Convert and upgrade your repository in a multi-stage process, per the instructions starting on page 3-3.
- ▶ File in your GemStone kernel class changes.
- ▶ Recompile and relink any C user actions or client applications.
- ▶ Recompile and relink any C or C++ user actions or client applications.
- ▶ Reload client Smalltalk images.

The architecture of the repository in GemStone/S 64 Bit 2.3 is significantly different from GemStone/S 64 Bit 1.x. For that reason, the upgrade from v1.x to v2.3 is a conversion that

cannot be done in place. The upgrade conversion process will construct a new GemStone/S 64 Bit repository, using the 1.x repository as a template. When the conversion is completed, both the 1.x and 2.3 repositories will exist. This means that enough disk space must be available to accommodate both repositories.

The GemStone/S 64 Bit 2.3 repository will be substantially larger than the GemStone/S 64 Bit 1.x repository. Repository size increases between 20% and 200% or more are likely, depending on the nature of the data in the repository.

The conversion process will not substantially modify the original 1.x repository. The 1.x repository will remain in a fully usable and coherent state after the conversion is completed.

## Conversion Strategy

We recommend that you perform the upgrade conversion twice: first a pilot conversion and then the production conversion. With this strategy, you can keep your version 1.x production system running while you familiarize yourself with the conversion process. The steps are the same for the pilot and the production conversions; where there are difference, this is noted in the instructions.

If possible, the pilot conversion should be done on a copy of your production system. During the pilot conversion, the database integrity is verified before and after conversion, and growth information on the repository is determined that will allow you to configure the final version 2.3 system correctly.

## Conversion Procedure

The conversion procedure from GemStone/S 64 Bit 1.x to GemStone/S 64 Bit 2.3 is performed in several stages. The first stage executes in the existing 1.x environment, that is, with \$GEMSTONE pointing to the GemStone/S 64 Bit v1.x product tree. Do not reset \$GEMSTONE until specified in the instructions. The following phases of conversion execute in the GemStone/S 64 Bit environment.

The following list summarizes the steps necessary to perform the conversion to GemStone/S 64 Bit v2.3.

- ▶ Preprocessing in Old Environment .....3-3
- ▶ Prepare for Conversion .....3-5
- ▶ Perform the Conversion and Upgrade .....3-6
- ▶ Restore Your Site-Specific Settings and Back Up the Repository .....3-9

### NOTE

*The following instructions use the version number 1.2.5 to represent any GemStone/S 64 Bit 1.x version, 1.2 or later. Any differences in the upgrade procedure are noted in the instructions.*

## Preprocessing in Old Environment

1. Install GemStone/S 64 Bit 2.3 to a new installation directory, separate from the installation directory for 1.2.5, as described in Chapter 1 of this Installation Guide.

Define a new environment variable, `$GEMSTONE_64`, to point to this product tree. At this point, do not reset `$GEMSTONE` or update the path to point to v2.3.

For example, using the default GemStone/S 64 Bit 2.3 installation location from Chapter 1:

C shell:

```
% setenv GEMSTONE_64 <InstallDir>/GemStone64Bit2.3.0-<platform>
```

Bourne or Korn shell:

```
$ GEMSTONE_64=<InstallDir>/GemStone64Bit2.3.0-<platform>
$ export GEMSTONE_64
```

2. Check the system configuration file used by your existing version 1.2.5 installation. If the environment variable `$GEMSTONE` is used in the paths for extent file locations in the `DBF_EXTENT_NAMES`, this must be changed to use the absolute path. The conversion will not proceed with `$GEMSTONE` in the extent file path/s.
3. If this is the pilot conversion, to verify the integrity of your v1.2.5 system, run an object audit and a page audit prior to conversion. For the page audit, which requires the stone to be shut down, you may choose to run this following the `convprep` step (step on page 3-4).

For instructions in running object and page audits, see the *System Administration Guide for GemStone/S 64 Bit*

4. Optional: Set up classes for list instances.

Some customers may need to perform application level object conversions on their repository, after the GemStone conversion has completed. For such applications, GemStone can be instructed to create lists of instances of particular classes during conversion. This behavior is not enabled by default. To enable, you must define a UserGlobal with a specific name and structure. Collecting the lists of instances will slow down the conversion process; larger numbers of classes and instances of these classes will slow down the conversion more.

To collect lists of instance of classes, before invoking the `convprep1x` script, do the following:

- a. Determine the list of classes for which instances are to be collected by the conversion.
- b. Login to the v1.2.5 system as SystemUser and ensure you are in transaction.
- c. Create an IdentitySet containing one of more classes for which instances are to be located.
- d. Store the IdentitySet in UserGlobals under the key `#ConversionClassesToFind`.
- e. Commit the transaction.

During the execution of the `convprep1x` script, if the symbol `#ConversionClassesToFind` is found, information is written to the text file `$upgradeLogDir/ClassesForListInstances.txt`. Results are written to bitmap files which can be loaded into the final converted GemStone/S 64 Bit v2.3 repository.

5. Log in to the v1.2.5 system and reset the SystemUser password to 'swordfish':

```
topaz 1> printit
(AllUsers userWithId: #SystemUser) password: 'swordfish' .
System commitTransaction .
%
```

The conversion scripts log in with the SystemUser account and the default password.

6. Halt all user activity on the repository you are going to convert:

- a. Log in to Topaz as DataCurator.
- b. Force all other users off the system:

```
topaz 1> printit
System stopUserSessions.
%
```

#### CAUTION

*You MUST file out any changes that you have made to the GemStone/S 64 Bit kernel classes in order to preserve these changes in version 2.3. Also, consider saving important modified files, such as configuration files, that will be overwritten during the conversion.*

7. File out any modifications or additions you made to GemStone/S 64 Bit kernel class methods by using the Topaz command **fileout**. For more information about fileout, see the *GemStone Topaz Programming Environment*.
8. Logout, and exit topaz.
9. Set the environment variable that will hold the upgrade log files.

C shell:

```
% setenv upgradeLogDir tempDir
```

Bourne or Korn shell:

```
$ upgradeLogDir=tempDir
$ export upgradeLogDir
```

Where *tempDir* is a temporary directory for which you have write permission.

#### NOTE

*Use a separate log directory for each repository you convert.*

Run the GemStone/S 64 Bit 2.3 script `convprep1x`. This script is in the upgrade directory of the 2.3 product tree; this should not be in your path, so it will need to be invoked with an explicit path. For example,

```
% $GEMSTONE_64/upgrade/convprep1x
```

This script has the following options:

```
convpreplx [-h] [-s <stonename>] [-c] [-n <numcachewarmers>]
-c prewarm the cache using startcachewarmers (default: no prewarm)
-h prints this usage information.
-n <numcachewarmers> where <numcachewarmers> is the number of
cachewarmer gems to start. Defaults to 1 if no number specified; has no effect if -c is
not specified.
-s <stoneName> sets the name of the running v1.2.5 Stone to scan; if this option is
not used, the script will default to gs64stone.
```

The **convpreplx** script scans the v1.2.5 repository and produces files that are used in the second phase of conversion. These files are written to `$upgradeLogDir`. The **convpreplx** script will write progress messages to stdout. When it completes, it will report:

```
convpreplx[INFO]: ...conversion preparation complete.
```

This script also shuts down the Stone.

## Prepare for Conversion

1. Set up the configuration for GemStone/S 64 Bit 2.3. In particular, you should examine and update:
  - a. **DBF\_EXTENT\_SIZES**. The conversion process creates new v2.3 extents based on the v1.2.5 extents; the v2.3 extents will be 20% to 200% larger. If this is the pilot, estimate the new size; if you are pre-growing extents allow for the larger growth.

For the production conversion, set the new sizes based on growth information from the pilot conversion.
  - b. **DBF\_PRE\_GROW**. We recommend setting this to true for the conversion process, in particular for the production conversion. This ensures that you will not run out of disk space during the conversion process.
  - c. **STN\_TRAN\_LOG\_DIRECTORIES**. For large repositories, we recommend setting the tranlogs to `/dev/null` for the conversion process. Tranlogs from the conversion process are not useful.
  - d. **SHR\_PAGE\_CACHE\_SIZE\_KB**. To ensure the performance of the v2.3 system equals that of the v1.2.5 system, the shared page cache size, for all shared caches including the gem server SPC, should be increased by the same percentage as the growth in the extent files. If this is the pilot, start by estimating this to increase by 50%. It is important that the entire object table fit into the SPC.

For the production conversion, use the increase computed from growth information from the pilot conversion.

**GEM\_TEMPOBJ\_CACHE\_SIZE**, **GEM\_PRIVATE\_PAGE\_CACHE\_KB**, and **STN\_PRIVATE\_PAGE\_CACHE\_KB** do not need to be increased.
2. Ensure that you have adequate disk space for the v2.3 extents in addition to the v1.2.5 extents, as well as for tranlogs (if not using `/dev/null`) and a backup following the conversion.

For the pilot conversion, allow for a growth of as much as 200%. In other words, if your repository extents total size currently is 1GB, ensure you have at least 2GB free space for the extents.

3. Set the `$GEMSTONE` and `$path` environment variables required for GemStone/S 64 Bit.

C shell:

```
% setenv GEMSTONE InstallDir23
% set path = ($GEMSTONE/bin $path)
```

Bourne or Korn shell:

```
$ GEMSTONE=InstallDir23
$ export GEMSTONE
$ export PATH=$GEMSTONE/bin:$PATH
```

where *InstallDir23* is the GemStone/S 64 Bit version 2.3 installation. You will no longer need the `$GEMSTONE_64` environment variable.

The `$upgradeLogDir` environment variable that was defined in the section 'Preprocessing in Old Environment' must be available and set to the same directory.

4. Copy a clean v2.3 `extent0.dbf` to the location specified by the first entry in the of extent files, as it appears in the `DBF_EXTENT_NAMES` parameter setting in the configuration file that will be used by the 2.3 repository. For example,

```
% cp $GEMSTONE/bin/extent0.dbf $GEMSTONE/data
% chmod a+w $GEMSTONE/data/extent0.dbf
```

New extent files for v2.3 will be created as part of conversion. **Do not** copy your version 1.2.5 extent files. All 1.2.5 extents should be available in their 1.2.5 locations.

## Perform the Conversion and Upgrade

1. Start the 2.3 Stone

```
% startstone stoneName23
```

2. Extent conversion is performed by the script `conv1xTo2x`. This script is in the v2.3 product tree, and does not require an explicit path.

This script requires as an argument the configuration file used by the v1.2.5 installation. This configuration file must not have the extent file names specified using `$GEMSTONE`.

It also has optional switches to specify the Stone name, the number of gems performing the conversion, and the number of OOPs per commit.

This script also includes the `-L` switch that enables recording of all references to Large Integers, and the `-F` switch that enables recording of all references to SmallFloats or Floats. The conversion process does not convert instances of LargePositive- or LargeNegativeIntegers that fall within the new SmallIntegers range, nor instances of SmallFloat and Float that fall within the new SmallDouble range. Conversion of these can be done as an optional manual step following conversion. Note that using the `-L` or `-F` option will slow down the conversion process, since each object must be checked for references to instances of these classes.

```
conv1xTo2x -e <oldSysConf> [-h] [-s <stoneName>] [-n <numConversionGems>] [-o <oopsPerCommit>] [-L] [-F]
```

`-e <oldSysConf>` specifies the configuration file to use. This configuration file must contain the list of 1.2.5 extents to read data from. This is required; the script will not run without this information.

-h prints this usage information.  
 -s <stoneName> sets the name of the running stone to convert; if this option is not used, the script will default to **gs64stone**.  
 -n <numConversionGems> sets the number of parallel gems that will do the conversion; if this option is not used, the script will default to use one.  
 -o <oopsPerCommit> sets the number of oops per transaction; if this option is not used, the script will default to use 1000000.  
 -L During conversion, determine which objects reference one or more instances of LargePositiveInteger or LargeNegativeInteger and write the object IDs to the binary bitmap file: \$upgradeLogDir/AllLrgIntRefs.bm.  
 -F During conversion, determine which objects reference one or more instances of Float for SmallFloat and write the object IDs to the binary bitmap file: \$upgradeLogDir/AllFloatRefs.bm.

For example,

```
% conv1xTo2x -e installLocation125/data/system.conf -s stoneName23
```

The **conv1xTo2x** script will write progress messages to stdout. When it completes, it will report:

```
conv1xTo2x[INFO]: Successful conversion.
```

The stone will shut down at the completion of the **conv1xTo2x** step. This may take some time as the conversion gems terminate. Wait until the stone has completed and shut down before continuing.

### 3. Restart the 2.3 Stone

```
% startstone stoneName23
```

### 4. Run the script that performs the kernel class filein to upgrade the image.

The image upgrade is performed by the script **upgradeImageFrom1x**. This script has optional switches to specify the stone name and to set to size of the **GEM\_TEMPOBJ\_CACHE\_SIZE** used for the upgrade process.

```
upgradeImageFrom1x [-h] [-c <cacheSize>] [-s <stoneName>]
```

-h prints this usage information.  
 -c <cacheSize> sets the size of the **GEM\_TEMPOBJ\_CACHE\_SIZE**; if this is not used, the script will default to use a value of 200000.  
 -s <stoneName> sets the name of the running stone to upgrade; if this option is not used, the script will default to **gs64stone**.

For example,

```
% upgradeImageFrom1x -s stoneName23
```

The script will prompt you to press the return key to begin.

The script invokes subordinate scripts to complete the upgrade. The upgrade process will take some time.

The script should complete with the message:

```
Upgrade completed. No errors detected.
```

If not, please preserve the Stone log file and the contents of \$upgradeLogDir. Contact your internal GemStone support person or GemStone Technical Support.

- To convert large objects found during the conversion process, run the `postconv` script. This script has optional flags.

```
postconv [-c <numCacheWarmerGems>][-h][-s <stoneName>]
[-n <numberOfSessions>] [-t <tempObjCacheSize>]
-c <numCacheWarmerGems> specifies the number of cache warmer gems to start
before starting post conversion; if this is not specified, no cache warmer gems are
started.
-h prints this usage information.
-s <stoneName> sets the name of the running stone to scan; if this option is not
used, the script will default to gs64stone.
-n <numberOfSessions> sets the number of parallel sessions to run to perform the
large object conversion. If this option is not specified, the script will default to one.
-t <tempObjCacheSize> sets the size of GEM_TEMPOBJ_CACHE_SIZE in KB; by
default, the same value as that used in the upgradeImage step, which defaults to
200000.
```

For example,

```
% postconv -s stoneName23
```

The `postconv` script will write progress messages to stdout. When it completes, it will report:

```
postconv[INFO]: conversion process complete
```

- If this is the pilot conversion, run an object audit and a page audit to verify the integrity of the repository following the conversion.
- If you set up `#ConversionClassesToFind` in your v1.2.5 repository, be sure to remove this variable to avoid retaining references. Log in as `SystemUser`, execute:

```
UserGlobals removeKey: #ConversionClassesToFind.
```

and commit.

- Optional. If you set up `#ConversionClassesToFind` in your v1.2.5 repository in order to collect instances of specified classes, the results will be written to bitmap files in the `$upgradeLogDir` directory.

There will be one file per Class, the file will have a name of the form:

```
<ClassName>_<oldOop>_<newOop>.bm
```

where:

```
<className> - Name of the class .
<oldOop> - GemStone/S 64 Bit v1.2.5 OOP of the class.
<newOop> - GemStone/S 64 Bit v2.3 OOP of the class.
```

GemStone/S 64 Bit v2.3 contains Smalltalk methods to load bitmap files into customer-usable hidden sets. From these hidden sets, any required postconversion processing of the instances of these classes can be done.

9. Optional: if you specified tracking of references to Large Integers or Floats, by using the `-L` or `-F` option during the `conv1xTo2x` script execution, the results will be written to bitmap files:

```
$upgradeLogDir/AllLrgIntRefs.bitmap
$upgradeLogDir/AllFloatRefs.bitmap
```

GemStone/S 64 Bit v2.3 contains Smalltalk methods to load bitmap files into customer-usable hidden sets. From these hidden sets, you may load the individual objects and manually update the references from Large Integers to SmallIntegers, or from Float or SmallFloat to SmallDouble.

## Restore Your Site-Specific Settings and Back Up the Repository

1. Reinstall any other GemStone products that modify kernel classes.  
If you use GemConnect or GemBuilder for Java, you must install it again at this time. Use the procedure in the installation guide for this product.
2. Log in to GemStone/S 64 Bit version 2.3 as DataCurator.
3. Change the password for SystemUser, which you changed to `swordfish` prior to the conversion, back to its previous value. Also, change the passwords for GcUser and DataCurator, which were reset by the conversion process, back to the version previous value:

```
topaz 1> printit
(AllUsers userWithId: 'SystemUser') password: '125Password'.
(AllUsers userWithId: 'GcUser') password: '125Password'.
(AllUsers userWithId: 'DataCurator') password: '125Password'.
System commitTransaction
%
```

where `125Password` is the account password used in the original GemStone/S 64 Bit v1.2.5 repository.

The converted repository is now usable. Other users can log in to assist with the following steps.

4. If you have modified any kernel class methods of the previous version, carefully compare your changes with version 2.3 kernel methods to see whether your changes are still necessary or appropriate. If so, file in the changes and commit.
5. Create a full backup of the converted repository. For details, see the *System Administration Guide for GemStone/S 64 Bit*.
6. If you are using GBS clients, configure these to use the version 2.3 client libraries. See Chapter 5, 'Configuring GBS for GemStone/S 64 Bit' for details



# Converting from GemStone/S 6.x

This chapter describes how to convert an existing GemStone/S installation to GemStone/S 64 Bit version 2.3. GemStone/S 64 Bit version 2.3 supports upgrade from GemStone/S version 6.3 or later. If you are converting from 6.1.x, you must first upgrade to version 6.3 or later, before converting to GemStone/S 64 Bit version 2.3.

While GemStone/S is similar to GemStone/S 64 Bit, there are differences in code and administration. Conversion to GemStone/S 64 Bit requires modifications to your existing application.

As part of the conversion process, you:

- ▶ Modify classes and methods that run in GemStone so they work properly with the GemStone/S 64 Bit classes and methods.
- ▶ Modify your application's client code as necessary. This code may be in C, C++, or client Smalltalk.

*NOTE*

*In order to use GemBuilder for Smalltalk (GBS) with the GemStone/S 64 Bit v2.3 server, you may need to upgrade your GBS version, and configure it correctly for use with GemStone/S 64 Bit. See the supported versions and configuration instructions in Chapter 5 of this Installation Guide.*

- ▶ Ensure you have no methods whose compiled size is larger than 64K. Methods larger than 64K will not fail during conversion, but cannot be loaded or executed in GemStone/S 64 Bit. For more information, see "Detecting Oversize Methods" on page 4-10.
- ▶ File out the changes to GemStone kernel classes.
- ▶ Convert and upgrade your repository in a multi-stage process per the instructions starting on page 4-3.
- ▶ File in your GemStone kernel class changes.
- ▶ Recompile and relink any C user actions or client applications.

- ▶ Recompile and relink any C or C++ user actions or client applications.
- ▶ Reload client Smalltalk images.

The architecture of the repository in GemStone/S 64 Bit 2.3 is substantially different from GemStone/S 6.3. For that reason, the upgrade from v6.3 to v2.3 is a conversion that cannot be done in place. The upgrade conversion process will construct a new GemStone/S 64 Bit repository, using the 6.3 repository as a template. When the conversion is completed, both the 6.3 and 2.3 repositories will exist. This means that enough disk space must be available to accommodate both repositories.

The GemStone/S 64 Bit 2.3 repository will be substantially larger than the GemStone/S 6.3 repository. Repository size increases between 20% and 200% or more are likely, depending on the nature of the data in the repository.

The conversion process will not substantially modify the original 6.3 repository. The 6.3 repository will remain in a fully usable and coherent state after the conversion is completed.

## Conversion Strategy

We recommend that you perform the upgrade conversion twice: first a pilot conversion and then the production conversion. With this strategy, you can keep your version 6.3 production system running while you familiarize yourself with the conversion process. The steps are the same for the pilot and the production conversions; where there are difference, this is noted in the instructions.

If possible, the pilot conversion should be done on a copy of your production system. During the pilot conversion, the database integrity is verified before and after conversion, and growth information on the repository is determined that will allow you to configure the final version 2.3 system correctly.

## Conversion Procedure

The conversion procedure from GemStone/S 6.3 to GemStone/S 64 Bit 2.3 is performed in several stages. The first stage executes in the existing 6.3 environment, that is, with \$GEMSTONE pointing to the GemStone/S v6.3 product tree. Do not reset \$GEMSTONE until specified in the instructions. The following phases of conversion execute in the GemStone/S 64 Bit environment.

The following list summarizes the steps necessary to perform the conversion to GemStone/S 64 Bit v2.3.

- ▶ Preprocessing in Old Environment ..... 4-3
- ▶ Prepare for Conversion ..... 4-5
- ▶ Perform the Conversion and Upgrade ..... 4-6
- ▶ Restore Your Site-Specific Settings and Back Up the Repository ..... 4-9

## Preprocessing in Old Environment

1. File out any modifications or additions you made to GemStone/S kernel class methods by using the Topaz command **fileout**. For more information about fileout, see the *GemStone Topaz Programming Environment*.

You will need to carefully compare these changes with GemStone/S 64 Bit 2.3 kernel methods to determine whether your changes are still relevant or appropriate.

2. Verify that you have no methods larger than 64K. This must be done prior to conversion. Oversize methods do not cause an error in the conversion, but cannot be loaded or executed in the converted repository. GemStone/S 64 Bit 2.3 provides a tool to assist in detecting oversize methods - see "Detecting Oversize Methods" on page 4-10
3. Install GemStone/S 64 Bit 2.3 to a new installation directory, separate from the installation directory for 6.3, as described in Chapter 1 of this Installation Guide.

Define a new environment variable, `$GEMSTONE_64`, to point to this product tree. At this point, do not reset `$GEMSTONE` or update the path to point to v2.3.

For example, using the default GemStone/S 64 Bit 2.3 installation location from Chapter 1:

C shell:

```
% setenv GEMSTONE_64 <InstallDir>/GemStone64Bit2.3.0-<platform>
```

Bourne or Korn shell:

```
$ GEMSTONE_64=<InstallDir>/GemStone64Bit2.3.0-<platform>
$ export GEMSTONE_64
```

4. Check the system configuration file used by your existing version 6.3 installation. If the environment variable `$GEMSTONE` is used in the paths for extent file locations in the `DBF_EXTENT_NAMES`, this must be changed to use the absolute path. The conversion will not proceed with `$GEMSTONE` in the extent file path/s.
5. If this is the pilot conversion, to verify the integrity of your v6.3 system, run an object audit and a page audit prior to conversion. For the page audit, which requires the stone to be shut down, you may choose to run this following the `convprep6x` step (step 13 on page 4-5).

For instructions in running object and page audits, see the *System Administration Guide*.

6. Prior to conversion, ensure there are no dead objects in your repository.
7. Optional: Set up classes for list instances.

Some customers may need to perform application level object conversions on their repository, after the GemStone conversion has completed. For such applications, GemStone can be instructed to create lists of instances of particular classes during conversion. This behavior is not enabled by default. To enable, you must define a UserGlobal with a specific name and structure. Collecting the lists of instances will slow down the conversion process; larger numbers of classes and instances of these classes will slow down the conversion more.

To collect lists of instance of classes, before invoking the `convprep6x` script, do the following:

- a. Determine the list of classes for which instances are to be collected by the conversion.
- b. Login to the v6.3 system as SystemUser and ensure you are in transaction.
- c. Create an IdentitySet containing one of more classes for which instances are to be located.
- d. Store the IdentitySet in UserGlobals under the key #ConversionClassesToFind.
- e. Commit the transaction.

During the execution of the `convprep6x` script, if the symbol #ConversionClassesToFind is found, information is written to the text file `$upgradeLogDir/ClassesForListInstances.txt`. Results are written to bitmap files which can be loaded into the final converted GemStone/S 64 Bit v2.3 repository.

8. Log in to the v6.3 system and reset the SystemUser password to 'swordfish':

```
topaz 1> printit
(AllUsers userWithId: #SystemUser) password: 'swordfish' .
System commitTransaction .
%
```

The conversion scripts log in with the SystemUser account and the default password.

9. Halt all user activity on the repository you are going to convert:

- a. Log in to Topaz as DataCurator.
- b. Force all other users off the system:

```
topaz 1> printit
System stopOtherSessions.
%
```

#### CAUTION

*You MUST file out any changes that you have made to the GemStone/S kernel classes in order to preserve these changes in version 2.3. Also, consider saving important modified files, such as configuration files, that will be overwritten during the conversion.*

10. File out any modifications or additions you made to GemStone/S kernel class methods by using the Topaz command **fileout**. For more information about fileout, see the *GemStone Topaz Programming Environment*.
11. Logout, and exit topaz.
12. Set the environment variable that will hold the upgrade log files.

C shell:

```
% setenv upgradeLogDir tempDir
```

Bourne or Korn shell:

```
$ upgradeLogDir=tempDir
$ export upgradeLogDir
```

Where *tempDir* is a temporary directory for which you have write permission.

*NOTE*

*Use a separate log directory for each repository you convert.*

13. Run the GemStone/S 64 Bit 2.3 script **convprep6x**. This script is in the upgrade directory of the 2.3 product tree; this should not be in your path, so it will need to be invoked with an explicit path. For example,

```
% $GEMSTONE_64/upgrade/convprep6x
```

This script has the following options:

```
convprep6x [-h] [-s <stonename>]
```

-h prints this usage information.

-s <stoneName> sets the name of the running v6.3 Stone to scan; if this option is not used, the script will default to **gemserver63**.

The **convprep6x** script scans the v6.3 repository and produces files that are used in the second phase of conversion. These files are written to **\$upgradeLogDir**. The **convprep6x** script will write progress messages to stdout. When it completes, it will report:

```
convprep6x[INFO]: ...conversion preparation complete.
```

If this output is not produced, check the log files in the **\$upgradeLogDir** directory for information.

This script also shuts down the Stone.

## Prepare for Conversion

1. Set up the configuration for GemStone/S 64 Bit 2.3. In particular, you should examine and update:
  - a. **DBF\_EXTENT\_SIZES**. The conversion process creates new v2.3 extents based on the v6.3 extents; the v2.3 extents will be 20% to 200% larger. If this is the pilot, estimate the new size; if you are pre-growing extents allow for the larger growth.  
For the production conversion, set the new sizes based on growth information from the pilot conversion.
  - b. **DBF\_PRE\_GROW**. We recommend setting this to true for the conversion process, in particular for the production conversion. This ensures that you will not run out of disk space during the conversion process.
  - c. **STN\_TRAN\_LOG\_DIRECTORIES**. For large repositories, we recommend setting the tranlogs to `/dev/null` for the conversion process. Tranlogs from the conversion process are not useful.
  - d. **SHR\_PAGE\_CACHE\_SIZE\_KB**. To ensure the performance of the v2.3 system equals that of the v6.3 system, the shared page cache size, for all shared caches including the gem server SPC, should be increased by the same percentage as the

growth in the extent files. If this is the pilot, start by estimating this to increase by 50%. It is important that the entire object table fit into the SPC.

For the production conversion, use the increase computed from growth information from the pilot conversion.

`GEM_TEMPOBJ_CACHE_SIZE`, `GEM_PRIVATE_PAGE_CACHE_KB`, and `STN_PRIVATE_PAGE_CACHE_KB` do not need to be increased.

2. Ensure that you have adequate disk space for the v2.3 extents in addition to the v6.3 extents, as well as for tranlogs (if not using `/dev/null`) and a backup following the conversion.

For the pilot conversion, allow for a growth of as much as 200%. In other words, if your repository extents total size currently is 1GB, ensure you have at least 2GB free space for the 2.3 extents.

3. Set the `$GEMSTONE` and `$path` environment variables required for GemStone/S 64 Bit.

C shell:

```
% setenv GEMSTONE InstallDir23
% set path = ($GEMSTONE/bin $path)
```

Bourne or Korn shell:

```
$ GEMSTONE=InstallDir23
$ export GEMSTONE
$ export PATH=$GEMSTONE/bin:$PATH
```

where `InstallDir23` is the GemStone/S 64 Bit version 2.3 installation. You will no longer need the `$GEMSTONE_64` environment variable.

The `$upgradeLogDir` environment variable that was defined in the section 'Preprocessing in Old Environment' (see step 12 on page 4-4) must be available and set to the same directory.

4. Copy a clean v2.3 `extent0.dbf` to the location specified by the first entry in the of extent files, as it appears in the `DBF_EXTENT_NAMES` parameter setting in the configuration file that will be used by the 2.3 repository. For example,

```
% cp $GEMSTONE/bin/extent0.bdf $GEMSTONE/data
% chmod a+w $GEMSTONE/data/extent0.dbf
```

New extent files for v2.3 will be created as part of conversion. **Do not** copy your version 6.3 extent files. All 6.3 extents should be available in their 6.3 locations.

## Perform the Conversion and Upgrade

1. Start the 2.3 Stone

```
% startstone stoneName64
```

2. Extent conversion is performed by the script `conv6xTo2x`. This script is in the v2.3 product tree, and does not require an explicit path.

This script requires as an argument the configuration file used by the v6.3 installation. This configuration file must not have the extent file names specified using `$GEMSTONE`.

It also has optional switches to specify the Stone name, the number of gems performing the conversion, and the number of OOPs per commit.

This script also includes the `-L` switch that enables recording of all references to Large Integers, and the `-F` switch to record all references to Float or SmallFloat. The conversion process does not convert instances of LargePositive- or LargeNegativeIntegers that fall within the new SmallIntegers range, nor instances of Float or SmallFloat that are representable as instances of SmallDouble. This can be done as an optional manual step following conversion. Note that using the `-L` or `-F` options will slow down the conversion process, since each object must be checked for references.

```
conv6xTo2x -e <oldSysConf> [-h] [-s <stoneName>] [-n <numConversionGems>] [-o <oopsPerCommit>] [-F] [-L]
```

`-e <oldSysConf>` specifies the configuration file to use. This configuration file must contain the list of 6.3 extents to read data from. This is required; the script will not run without this information.

`-h` prints this usage information.

`-s <stoneName>` sets the name of the running stone to convert; if this option is not used, the script will default to **gs64stone**.

`-n <numConversionGems>` sets the number of parallel gems that will do the conversion; if this option is not used, the script will default to use one.

`-o <oopsPerCommit>` sets the number of oops per transaction; if this option is not used, the script will default to use 1000000.

`-F` During conversion, determine which objects reference one or more instances of Float for SmallFloat and write the object IDs to the binary bitmap file: `$upgradeLogDir/AllFloatRefs.bm`.

`-L` During conversion, determine which objects reference one or more instances of LargePositiveInteger or LargeNegativeInteger and write the object IDs to the binary bitmap file: `$upgradeLogDir/AllLrgIntRefs.bm`

For example,

```
% conv6xTo2x -e installLocation63/data/system.conf -s stoneName64
```

The `conv6xTo2x` script will write progress messages to stdout. When it completes, it will report:

```
conv6xTo2x[INFO]: Successful conversion.
```

The stone will shut down at the completion of the `conv6xTo2x` step. This may take some time as the conversion gems terminate. Wait until the stone has completed and shut down before continuing.

### 3. Restart the 2.3 Stone

```
% startstone stoneName64
```

### 4. Run the script that performs the kernel class filein to upgrade the image.

The image upgrade is performed by the script `upgradeImageFrom6x`. This script has optional switches to specify the stone name and to set to size of the `GEM_TEMPOBJ_CACHE_SIZE` used for the upgrade process.

```
upgradeImageFrom6x [-h] [-c <cacheSize>] [-s <stoneName>]
-h prints this usage information.
-c <cacheSize> sets the size of the GEM_TEMPOBJ_CACHE_SIZE; if this is not
used, the script will default to use a value of 100000.
-s <stoneName> sets the name of the running stone to upgrade; if this option is
not used, the script will default to gs64stone.
```

For example,

```
% upgradeImageFrom6x -s stoneName23
```

The script will prompt you to press the return key to begin.

The script invokes subordinate scripts to complete the upgrade. The upgrade process will take some time.

The script should complete with the message:

```
Upgrade completed. No errors detected.
```

If not, please preserve the Stone log file and the contents of `$upgradeLogDir`. Contact your internal GemStone support person or GemStone Technical Support.

5. To convert large objects found during the conversion process, run the `postconv` script. This script has optional flags to specify stone name and the number of sessions to use.

```
postconv [-c <numCacheWarmerGems>][[-h]][-s <stoneName>]
[-n <numberOfSessions>] [-t <tempObjCacheSize>]
-c <numCacheWarmerGems> specifies the number of cache warmer gems to start
before starting post conversion; if this is not specified, no cache warmer gems are
started.
-h prints this usage information.
-s <stoneName> sets the name of the running stone to scan; if this option is not
used, the script will default to gs64stone.
-n <numberOfSessions> sets the number of parallel sessions to run to perform the
large object conversion. If this option is not specified, the script will default to one.
-t <tempObjCacheSize> sets the size of GEM_TEMPOBJ_CACHE_SIZE in KB; by
default, the same value as that used in the upgradeImage step, which defaults to
200000.
```

For example,

```
% postconv -s stoneName64
```

The `postconv` script will write progress messages to stdout. When it completes, it will report:

```
postconv[INFO]: Success! Conversion process from GemStone 6.3.x
to GemStone64 2.x completed.
```

6. If this is the pilot conversion, run an object audit and a page audit to verify the integrity of the repository following the conversion.

- If you set up #ConversionClassesToFind in your v6.3 repository, be sure to remove this variable to avoid retaining references. Log in as SystemUser, execute:

```
UserGlobals removeKey: #ConversionClassesToFind.
```

and commit.

- Optional. If you set up #ConversionClassesToFind in your v6.3 repository in order to collect instances of specified classes, the results will be written to bitmap files in the \$upgradeLogDir directory.

There will be one file per Class, the file will have a name of the form:

```
<ClassName>_<oldOop>_<newOop>.bm
```

where:

<className> - Name of the class.

<oldOop> - GemStone/S v6.3 OOP of the class.

<newOop> - GemStone/S 64 Bit v2.3 OOP of the class.

GemStone/S 64 Bit v2.3 contains Smalltalk methods to load bitmap files into customer-usable hidden sets. From these hidden sets, any required postconversion processing of the instances of these classes can be done.

- Optional: if you specified tracking of references to Large Integers or Floats, by using the -L or -F options during the conv6xTo2x script execution, the results will be written to a bitmap file:

```
$upgradeLogDir/AllLrgIntRefs.bm
```

```
$upgradeLogDir/AllFloatRefs.bm
```

GemStone/S 64 Bit v2.3 contains Smalltalk methods to load bitmap files into customer-usable hidden sets. From these hidden sets, you may load the individual objects and manually update the references.

## Restore Your Site-Specific Settings and Back Up the Repository

- Reinstall any other GemStone products that modify kernel classes.

If you use GemConnect or GemBuilder for Java, you must install it again at this time. Use the procedure in the installation guide for that product.

- Log in to GemStone/S 64 Bit version 2.3 as DataCurator.
- Change the password for SystemUser, which you changed to swordfish prior to the conversion, back to its previous value. Also, change the passwords for GcUser and DataCurator, which were reset by the conversion process, back to the version previous value:

```
topaz 1> printit
```

```
(AllUsers userWithId: 'SystemUser') password: '63Password'.
```

```
(AllUsers userWithId: 'GcUser') password: '63Password'.
```

```
(AllUsers userWithId: 'DataCurator') password: '63Password'.
```

```
System commitTransaction
```

```
%
```

where *63Password* is the account password used in the original GemStone/S v6.3 repository.

The converted repository is now usable. Other users can log in to assist with the following steps.

4. If you have modified any kernel class methods of the previous version, carefully compare your changes with version 2.3 kernel methods to see whether your changes are still necessary or appropriate. If so, file in the changes and commit.
5. Create a full backup of the converted repository. For details, see the *System Administration Guide for GemStone/S 64 Bit*.
6. If you are using GBS clients, configure these to use the version 2.3 client libraries. See Chapter 5, 'Configuring GBS for GemStone/S 64 Bit' for details.

## Detecting Oversize Methods

Methods larger than 65K are not supported in GemStone/S 64 Bit, and cannot be loaded or executed. If your GemStone/S version 6.3 repository contains methods larger than this limit, these methods must be factored into multiple smaller methods before the repository is converted; this task cannot be done after conversion.

GemStone/S 64 Bit 2.3 provides a script to detect if any methods exceed the size limit. To use this script, the GemStone/S version 6.3 repository that you wish to verify must be running, and not yet converted to GemStone/S 64 Bit, and GemStone/S 64 Bit 2.3 must have been installed.

1. Ensure that a stone is running on the GemStone/S version 6.3 repository.
2. Verify that GemStone/S 64 Bit 2.3 is installed
3. Start topaz, and log in to the GemStone/S version 6.3 repository as SystemUser.
4. Execute the script `methodsTooLargeFor64.topaz`. For example,  

```
topaz 1>input gs64install/upgrade/methodsTooLargeFor64.topaz
```

where *gs64install* is the installation directory for GemStone/S 64 Bit 2.3.
5. Wait for the scan to complete. This will take some time as it scans all extents for instances of GsMethod. When it completes, log out and exit topaz.
6. The script prints the results of the scan both to standard out and to a text file `methodsToLargeFor64Report.log`, in the working directory. This report provides details on any methods that are exceed the size limit, including the current size, class and selector. If there are methods that exceed the size limit, factor these into multiple smaller methods and commit.
7. Execute a `markForCollection` and allow reclaim to complete, before rerunning the script to verify that the modified methods are now of appropriate size. Otherwise, the script may detect old instances of methods that have not yet been garbage collected.

---

Chapter  
5

# Configuring GBS for GemStone/S 64 Bit

This chapter describes how to configure your GemBuilder for Smalltalk (GBS) application to run with GemStone/S 64 Bit version 2.3.

*NOTE*

*GemStone/S 64 Bit version 2.3 requires the use of GBS version 7.1.2 or later; version 7.2.1 or later is recommended. Versions earlier than 7.1.1 cannot log in to GemStone/S 64 Bit 2.3; version 7.1.1 may be usable, but some GBS behavior such as the Segment Tool will be incorrect for versions prior to 7.1.2. For upgrade instructions, refer to the GemBuilder for Smalltalk Installation Guide.*

For the supported versions of VisualWorks client Smalltalk, see “Supported platforms” on page 5-2

In addition to using the appropriate version of GBS, you must use GemStone/S 64 Bit 2.3 client libraries to be able to log in to the GemStone/S 64 Bit 2.3 server. Applications using GBS version 7.1.x can log in to either GemStone/S or GemStone/S 64 Bit repositories (but not simultaneously), provided that the appropriate client libraries for each are used.

Note that GBS version 7.2 and later use a new interface to the server, and are not compatible with 32-bit GemStone/S or versions of GemStone/S 64 Bit earlier than v.2.2.4.

GemStone/S 64 Bit 2.3 supports only RPC logins from GBS; linked logins are not supported.

On Unix platforms, GemStone/S 64 Bit 2.3 provides both 64-bit libraries and 32-bit libraries. To load these libraries into the VisualWorks 32-bit process, the 32-bit libraries must be used. 64-bit and 32 bit libraries have identical names, and are provided in separate directories to distinguish them.

The following sections describes the procedure for installing client libraries and getting GBS to recognize them.

## Supported platforms

GBS version 7.2.1 is supported with GemStone/S 64 Bit version 2.3, on the following VisualWorks and OS platforms:

VisualWorks 7.6, with the 7.6 Object Engine, is supported on the following platforms:

- ▶ Windows XP, SP1 or later, Windows 2003, and Windows Vista
- ▶ Solaris 10 on x86
- ▶ HP-UX 11.11 on PA-RISC
- ▶ SUSE Linux ES 10 and RedHat Linux ES 5.0

VisualWorks 7.5, with the 7.5 Object Engine, is supported on the following platforms:

- ▶ Windows XP, SP1 or later, and Windows 2003
- ▶ HP-UX 11.11 on PA-RISC
- ▶ SUSE Linux ES 10

GBS version 7.1.2patch1 is supported with GemStone/S 64 Bit version 2.3, on the following VisualWorks and OS platforms:

VisualWorks 7.5, with the 7.5 Object Engine, is supported on the following platforms:

- ▶ Windows XP, SP1 or later, and Windows 2003
- ▶ Solaris 9 and 10 on SPARC
- ▶ HP-UX 11.11 on PA-RISC
- ▶ SUSE Linux ES 10

VisualWorks 7.4.1, with the 7.4d Object Engine, is supported on the following platforms:

- ▶ Windows XP, SP1 or later
- ▶ Solaris 9 and 10 on SPARC
- ▶ HP-UX 11.11 on PA-RISC
- ▶ SUSE Linux ES 10

VisualWorks 7.4, with the 7.4 Object Engine, is supported on the following platforms:

- ▶ Windows XP, SP1 or later
- ▶ Solaris 9 and 10 on SPARC
- ▶ HP-UX 11.11 on PA-RISC (with the 7.4d Object Engine)

VisualWorks 5i.1 Envy, with the 5i.4c Object Engine, is supported with GBS version 7.1.2 only, on the following platforms:

- ▶ Windows 2000, SP1 or later, and Windows XP, SP1 or later

## GemStone/S 64 Bit 2.3 Windows Client Installation

To allow GemStone/S 64 Bit clients to connect and perform some operations on Windows, GemStone/S 64 Bit provides a separate Windows installation, with the name GemBuilder for C. This installation provides:

- ▶ The ability to run topaz on Windows, to login RPC to a GemStone/S 64 Bit server on UNIX.
- ▶ The client libraries to be used by GBS for RPC logins.

If you do not require topaz on Windows, you may wish to extract only the client libraries from the Windows installation, and move these files to a directory on the path or to the GBS installation. See “Installing the GemStone/S 64 Bit 2.3 Libraries onto Windows Clients” on page 5-3

To install the GemStone/S 64 Bit Windows Client product, use the following procedure. The procedure is similar regardless of what platform the GemStone/S 64 Bit server is running on.

1. The GemStone/S 64 Bit client installation for Windows is provided as a zipped archive with a name similar to GemBuilderC2.3.0-x86.Windows\_NT.zip. Move this distribution file to the directory location in which this will be installed.
2. Create a directory named GemBuilderC2.3.0-x86.Windows\_NT, into which the client will be installed, and make this directory the working directory. For example:

```
C:\InstallDir> mkdir GemBuilderC2.3.0-x86.Windows_NT  
C:\InstallDir> cd GemBuilderC2.3.0-x86.Windows_NT
```

3. Unzip the distribution file using unzip. For example,

```
C:\InstallDir\GemBuilderC2.3.0-x86.Windows_NT> unzip  
GemBuilderC2.3.0-x86.Windows_NT.zip
```

In addition to several subdirectories, C:\InstallDir\GemBuilderC2.3.0-x86.Windows\_NT also contains two text files: PACKING.txt, which lists all of the GemStone files, and version.txt, which identifies the product and release.

4. Add the directory

```
C:\InstallDir\GemBuilderC2.3.0-x86.Windows_NT\bin
```

to the machine search path.

## Installing the GemStone/S 64 Bit 2.3 Libraries onto Windows Clients

This section describes the procedure for installing client libraries on Windows and getting GBS to recognize them.

1. Quit any running client Smalltalk VM that is using GBS.
2. Your client libraries may be placed in the directory in which the client Smalltalk executable resides, or in any directory that is on the path, %PATH%.

*NOTE*

*In step 3., <GBS> refers to the directory in which the client Smalltalk executable resides, or any directory that is on the path that will be used by the GBS application, and <SRC> refers to the GemStone/S 64 Bit Windows client installation directory (for example, installDir/GemBuilderC2.3.0-x86.Windows\_NT/bin).*

3. To copy the files from the GemStone/S 64 Bit Windows client directory <SRC> to the GemBuilder installation directory, or another directory on the Windows path, <GBS>, execute the following:

```
C:\> copy <SRC>\libgcirpc64-230.dll <GBS>
C:\> copy <SRC>\libgcirpc.dll <GBS>
C:\> copy <SRC>\libgs64-230.dll <GBS>
```

*NOTE*

*The shared library name includes exactly three digits of the server version number. If the server version number contains a larger or smaller number of digits, it is truncated or extended with zeros to make these three digits.*

4. Ensure that there are no other copies of these libraries on the search path.
5. If the GBS configuration parameter *libraryName* is not set, or is set to `libgcirpc.dll`, installation is complete. The correct client library will be loaded when the client Smalltalk VM is restarted and the application logs in to GemStone.

If you are converting from a different GemStone server product, your GBS application is likely to have set *libraryName* to the client library used with that product. This parameter needs to be updated for GemStone/S 64 Bit. If you are converting, continue with these instructions.

6. Start up the client Smalltalk VM.
7. Clear the library name. There are several ways to do this. Using the GBS settings dialog, select the tab titled "Server Communication", and clear the field `libraryName`. You may also execute:

```
GbsConfiguration current libraryName: ''
```

8. Save your image, exit, and restart, to allow the correct libraries to be loaded.

## Installing the GemStone/S 64 Bit 2.3 Libraries onto Unix Clients

GemStone/S 64 Bit supports GBS clients running on Solaris, Linux and HP-UX with 32-bit VisualWorks. Since the 64-bit libraries shipped with GemStone/S 64 Bit cannot be loaded into a 32-bit application, GemStone/S 64 Bit includes 32-bit versions of these libraries. These libraries can be found in the `lib32` subdirectory of the GemStone/S 64 Bit installation, `$GEMSTONE/lib32/`.

1. Log in to your GBS client machine as the user who is the owner of the GBS installation files.
2. Your client libraries may be placed in any directory that is on the machine search path `$LD_LIBRARY_PATH`, or you may add the directory containing the client libraries to the `$LD_LIBRARY_PATH`. Ensure that there are no other copies of the client libraries

on the search path. (In the following instructions, the term “path” means the path specified by `$LD_LIBRARY_PATH`)

Alternatively, you can place the shared libraries in any location, and in the GBS configuration parameter *libraryName*, specify the absolute path to the client library file.

*NOTE*

*In step 3., <GBS> refers to your GemBuilder installation directory, or any directory that is on the path that will be used by the GBS application, and <SRC> refers to the lib32 subdirectory of your installation (for example, installDir/GemStone64Bit2.3.0-sparc.Solaris/lib32).*

3. To copy the files from the GemStone/S 64 Bit server source directory *<SRC>* to the GemBuilder installation directory, or another directory, *<GBS>*, execute the following:

```
% cp <SRC>/libgcirpc64-230.so <GBS>
```

Note that the suffix on HP-UX is `.sl`, not `.so`; adjust the instructions for this platform.

*NOTE*

*The shared library name includes exactly three digits of the server version number. If the server version number contains a larger or smaller number of digits, it is truncated or extended with zeros to make these three digits.*

4. Make the destination directory the current working directory, and create a symbolic link to the library:

```
% cd <GBS>
% ln -s libgcirpc64-230.so libgcirpc.so
```

5. If the client libraries are in a directory on the path, and the GBS configuration parameter *libraryName* is not set, or is set to `libgcirpc.so`, installation is complete. The correct client library will be loaded after the client Smalltalk VM is restarted, on login.

If you are converting from a different GemStone server product, your GBS application is likely to have set *libraryName* to the client library used with that product. This parameter needs to be updated for GemStone/S 64 Bit. If you are converting, continue with these instructions.

6. Start up the client Smalltalk VM.
7. Set the library name. There are several ways to do this. Using the GBS settings dialog, select the tab titled “Server Communication”, and fill in the appropriate library name in the *libraryName* field. You may also execute:

```
GbsConfiguration current libraryName: '<libraryName>'
```

If the clientLibraries are in a directory on the path, clear the *libraryName* field, or set it to an empty string. The default client library search will find and load the correct library.

If the client libraries are not in a directory on the path, *libraryName* must be set to the absolute path and name of the client library `libgcirpc.so`.

8. Save your image, exit, and restart, to allow the correct libraries to be loaded.

